



**CZ** solution

## **CZ Print Release Station 6.0 --- Step by Step Configuration**

1. Components .....	2
2. Setup a Printer on Print Release Station .....	3
Option 1: Master Print Release Station is installed on a computer that will be used by staff or users to release the print jobs .....	3
Option 2: Master Print Release Station is installed on your current print server that has printers shared and and Slave Print Release Station is installed on a computer that will be used by staff or users to release the print jobs .....	7
3. Scenarios .....	12
3.1 CZ Print Release Station Staff-Mode .....	12
3.2 CZ Print Release Station User-Mode with Free Print Quotas .....	13
3.3 CZ Print Release Station User-Mode with Prepaid Account .....	15
3.4 CZ Print Release Station User-Mode with Self-Payment Equipment .....	16
3.5 CZ Print Release Station User-Mode with Login and Popup Notification .....	17
3.6 CZ Print Release Station User-Mode with Secure Card Reader Authenticator .....	21
3.7 CZ Print Release Station User-Mode with Windows Active Directory Authentication .....	22
4. Use Windows Group Policy to remotely install CZ Popup .....	23
5. Frequently Asked Questions .....	23

# 1. Components

CZ Print Release Station 6.0 includes the following components:

**Master Print Release Station (Required)** Master Print Release Station stores all configurations and holds all print jobs until they are released. It must be installed on a print server or a computer that can be used as a print server.

**CZ Popup (Optional Free Add-On)** CZ Popup is designed for print job notification, and it must be installed on the workstation. CZ Popup notifies users the print job information including document name, printer name, number of pages and total cost after they send a print job. It also allows users to change their print job name for their privacy, and (or) create a password that they can use to release their print jobs on the print release station, and (or) create a user id for their print jobs that they can use to show only their print jobs on the print release station (for some environments that students use their own laptops to print or environments that user id is not unique). CZ Popup can be run on Windows, Mac OSX / Classic or Linux client computers.


**CZ Print Job Report (Optional Free Add-On)** CZ Print Job Report is a Free Software allowing you to generate and view 94 reports including 54 default reports and 40 customized reports, and export these reports to Adobe-PDF, MS-Word, MS-Excel and Rich Text formats. These reports are designed for your print cost analysis.

**Slave Print Release Station (Optional)** The Slave Print Release Station can hold all print jobs or some of print jobs on the Master Print Release Station depending on the printer settings. Users can use either Master Print Release Station or Slave Print Release Station to release their print jobs.

**CZ Remote Cashier (Optional)** CZ Remote Cashier can be installed on any staff computer to manage prepaid account remotely.

## 2. Setup a Printer on Print Release Station

**Step 1.** Download and extract the [30-day trial version](#) of CZ Print Release Station, then double click **setup.exe** to install Master Print Release Station.




Option 1: Master Print Release Station is installed on a computer that will be used by staff or users to release the print jobs -- page 3 

Option 2: Master Print Release Station is installed on your current print server that has printers shared and Slave Print Release Station is installed on a computer that will be used by staff or users to release the print jobs – page 7

### Option 1: Master Print Release Station is installed on a computer that will be used by staff or users to release the print jobs


On the computer (e.g. \\PRS) where Master Print Release Station is installed:

**Step 2.** Click Start --> Settings --> Printers and Faxes (or Devices and Printers).




**Step 3.** Click "Add a printer" button to start the Add Printer Wizard, and then click Next.


**Step 4.** Click the "Local printer attached to this computer" option and then click Next.




**Step 5.** Select a port, for example Standard TCP/IP Port, Parallel / USB port or LPR Port and follow the instructions on screen. If the port is not in the list, select "Create a new port" to add a new port.




or



**Step 6.** The printer icon will be added to your Printers and Faxes folder (or Devices and Printers folder). Right click the printer icon and click Sharing.





**Step 7.** Right click the printer icon and click Properties. Uncheck "Render print jobs on client computers" and select "Start printing after last page is spooled".



**Step 8.** Click Start -> All Programs -> CZ Solution -> CZ Print Release Station 6.0 - Master to run CZ Print Release Station for the first time. If Preferences window doesn't appear, click menu Print Jobs -> Preferences.

**Step 9.** Click **Refresh List**, select the printers you want to control in the list of "Available Shared Printers" and click **Add** to add it to the list of "Monitored Printers", click **Save**, and then click **Exit**.




**Step 10.** On each workstation that you want to control the print jobs, add shared printer \\PRS\HP LaserJet 4:


- 9.1 Choose Start -> Printers and Faxes (or Devices and Printers).
- 9.2 Click "Add a printer" button to start the Add Printer Wizard, and then click Next.
- 9.3 Click the "A network printer" option and follow the instructions on screen.



9.4. The printer icon will be added to the Printers and Faxes folder (or Devices and Printers folder). The network printer name is like "**Printer-Name on Print-Server-Name**".




**Step 11.** Send a print job from a workstation. The print job is held in CZ Print Release Station -> Waiting Jobs. You can click Print button to release it. There are different ways to release print jobs. Please see [Scenarios](#) for more details.




**Option 2: Master Print Release Station is installed on your current print server that has printers shared and and Slave Print Release Station is installed on a computer that will be used by staff or users to release the print jobs**

On your current Print Server (e.g. \\PRS) that has shared printer (e.g. HP LaserJet 4)



**Step 2.** Click Start -> All Programs -> CZ Solution -> CZ Print Release Station 6.0 - Master to run CZ Print Release Station for the first time. If Preferences window doesn't appear, click menu Print Jobs -> Preferences.

**Step 3.** Click **Refresh List**, select the printers you want to control in the list of "Available Shared Printers" and click **Add** to add it to the list of "Monitored Printers".



**Step 4.** In Preferences -> Print Jobs, select "Enable add-on slave print release station", click **Save**, and then click **Exit**.

**Note:**

Master Print Release Station can be run as Windows service on your current print server regardless of whether someone is logged on.

Step 1. Exit Master Print Release Station if it is running.

Step 2. Rename file C:\Program Files\CZ Solution\CZ Print Release Station\config\noservice (or C:\Users\\AppData\Local\VirtualStore\Program Files\CZ Solution\CZ Print Release Station\config\noservice) to a different name.

Step 3. Start CZ Print Release Station and select the menu item "Tools-->Install CZ Print Release Station (Master) Service".


Step 4. Restart the computer. When the Master Print Release Station service is running, the process "PrintSaver.exe" is running in Task Manager.

If the Master Print Release Station is running at the backend on the print server and it is not used by users to release their print jobs, then only the license for Slave Print Release Station needs to be ordered. The license for Master Print Release Station is free.

If the Master Print Release Station is used by staff or users to release the print jobs, **don't install CZ Print Release Station (Master) Service.**

## Step 5. On a computer that will be Slave Print Release Station


5.1 Double click **CZ Print Release Station\_Slave.msi** to install Slave Print Release Station.




5.2 Choose Start -> Printers and Faxes (or Devices and Printers).

5.3 Click "Add a printer" button to start the Add Printer Wizard, and then click Next.


5.4 Click the "A network printer" option and follow the instructions on screen.



5.5 The printer icon will be added to the Printers and Faxes folder (or Devices and Printers folder). The network printer name is like "**Printer-Name on Print-Server-Name**".



5.6 Select menu Print Jobs --> Preferences, enter the IP address or computer name of print server where Master Print Release Station is installed, then click "Connect" and "Get Settings" button.



**Step 6.** Send a print job from a workstation to the network printer (For example \\PRS\HP LaserJet 4). The print job is held on both Master Print Release Station and Slave Print Release Station. You can click Print button to release it from either Master Print Release Station or Slave Print Release Station. There are different ways to release print jobs. Please see [Scenarios](#) for more details.

**CZ Print Release Station 5.0.0.3 - Master (Staff Mode)**

Print Jobs Document View Help Online Support

Refresh Preview Print Cancel Cancel All Preferences Printer Status Select All Save Help

Print Jobs

- Waiting Jobs
  - test
- Deleted Jobs
- Printed Jobs

User	Computer	Description	Pages	Cost	Submitted	Printer	Color	Duplex	Paper Size	Size
test	eaglepc	Test Page	1	0.10	1/5/2012 12:00:54 PM	HPC...	No	No	A4 210 x ...	90.00 KB

Selected Waiting Jobs      Total Pages: 1      Total Cost: 0.10

**CZ Print Release Station 5.0 - Slave (Staff Mode)**

Print Jobs Document View Help Online Support

Refresh Print Cancel Cancel All Preferences Printer Status Select All Save Help

Print Jobs

- Waiting Jobs
  - test

User	Computer	Description	Pages	Cost	Submitted	Printer	Color	Duplex	Paper Size	Size
test	eaglepc	Test Page	1	0.10	1/5/2012 12:00:54 PM	HPC...	No	No	A4 210 x ...	90.00 KB

Selected Waiting Jobs      Total Pages: 1      Total Cost: 0.10



### 3. Scenarios

#### 3.1 CZ Print Release Station Staff-Mode

1. A user sends a print job from a workstation.
2. CZ Print Release Station holds the print job with detail print job information.
3. The staff collects the payment and releases the print job for the user. The printing activity is recorded in the database of CZ Print Release Station.

**Note:** All unclaimed waiting jobs can be deleted automatically at the defined time in Preferences --> Print Jobs.


**Note:** The Waiting Jobs can be showed either by workstation name or user name. This can be set in “Preferences --> Print Jobs”.




**Note:** If the [Master – Slave infrastructure](#) is used, the print job can be listed on both the Master Print Release Station and the Slave Print Release Station and staff can use either one to release the print jobs.

### 3.2 CZ Print Release Station User-Mode with Free Print Quotas

**Step 1.** In Preferences --> Print Jobs, select either “Free printing for the first ## pages per day per person” or “Free printing for the first ## pages per term per person”. In Preferences --> User Mode, select "Lock the desktop in user mode" to lock Print Release Station computer in user mode and select "Auto switch to user mode when starting the application" to switch to user mode automatically when Print Release Station starts.



**Step 2.** In Menu Print Jobs, click "Switch to User Mode". You can switch back to Staff Mode by pressing "Alt" and "a" keys together, then enter the password defined in Preferences --> User Mode.




## Scenario


1. A user sends a print job from a workstation.
2. CZ Print Release Station holds the print job with detail print job information.
3. The user goes to the Print Release Station to release the print job. The job will not be printed out if the user's print quotas is not enough.

**Note:** All unclaimed waiting jobs can be deleted automatically at the defined time in Preferences --> Print Jobs.

**Note:** The Waiting Jobs can be showed either by workstation name or user name. This can be set in “Preferences --> Print Jobs”.



Print Jobs	User	Computer	Description	Pages	Cost	Submitted	Printer	Color	Duplex	Paper Size
Waiting Jobs	Nancy	Station3	Report - Notepad	16	1.60	7/16/2006 8:49:28 PM	Brother HL-5070N BR...	No	No	Letter 8 1/2 x 11
Gary	Gary	Station2	Microsoft Word -...	3	0.30	7/16/2006 8:47:01 PM	LAB_HPLaserJ5M	No	No	Letter 8 1/2 x 11
Nancy	Tom	Station4	Research.xls	1	0.10	7/16/2006 8:48:09 PM	LAB_HPLaserJ5M	No	No	Letter 8 1/2 x 11
Peter	Peter	Station5	Homework 1	5	0.50	7/16/2006 8:53:23 PM	LAB_HPLaserJ5M	No	No	Letter 8 1/2 x 11
Tom										



Print Jobs	User	Computer	Description	Pages	Cost	Submitted	Printer	Color	Duplex	Paper Size
Waiting Jobs	Nancy	Station3	Report - Notepad	16	1.60	7/16/2006 8:49:28 PM	Brother HL-5070N BR...	No	No	Letter 8 1/2 x 11
Station2	Gary	Station2	Microsoft Word -...	3	0.30	7/16/2006 8:47:01 PM	LAB_HPLaserJ5M	No	No	Letter 8 1/2 x 11
Station3	Tom	Station4	Research.xls	1	0.10	7/16/2006 8:48:09 PM	LAB_HPLaserJ5M	No	No	Letter 8 1/2 x 11
Station4	Peter	Station5	Homework 1	5	0.50	7/16/2006 8:53:23 PM	LAB_HPLaserJ5M	No	No	Letter 8 1/2 x 11
Station5										

**Note:** If the [Master – Slave infrastructure](#) is used, the print job can be listed on both the Master Print Release Station and the Slave Print Release Station and user can use either one to release their print jobs.

### 3.3 CZ Print Release Station User-Mode with Prepaid Account

**Step 1.** In Preferences --> User Mode, select "Use prepaid account and pin to release the print job".


**Step 2.** In Preferences --> Prepaid Accounts", click "Add" button to add a new account. The user account can also be imported from Windows Active Directory or a CSV file (You can export the users to CSV file, add / update that CSV file, then import it back). If the cost of each page is 0.10 in Preferences --> Printers, then balance 1.00 means the user can print 10 pages.



**Step 3.** In Menu Print Jobs, click "Switch to User Mode". You can switch back to Staff Mode by pressing "Alt" and "a" keys together, and then enter the password defined in Preferences --> User Mode.


### Scenario

1. A user sends a print job from a workstation.
2. CZ Print Release Station holds the print job with detail print job information.
3. The user goes to the Print Release Station and types the prepaid account and pin to release the print job. The job can't be printed out if there is not enough balance left for that user.



### 3.4 CZ Print Release Station User-Mode with Self-Payment Equipment

**Step 1.** In Preferences --> User Mode, select "Use self payment equipment".



**Step 2.** In Menu Print Jobs, click "Switch to User Mode". You can switch back to Staff Mode by pressing "Alt" and "a" keys together, and then enter the password defined in Preferences --> User Mode.


#### Scenario

1. A user sends a print job from a workstation.
2. CZ Print Release Station holds the print job with detail print job information.
3. The user goes to the Print Release Station and makes payment using coins, bill, debt card or credit card to release the print job.




### 3.5 CZ Print Release Station User-Mode with Login and Popup Notification

**Step 1.** In Preferences --> User Mode, select “Allow users to enter user id or computer name to show only their print jobs” and “Show popup notification when a print job is submitted on the workstation”.




**Step 2.** In Menu Print Jobs, click "Switch to User Mode". You can switch back to Staff Mode by pressing "Alt" and "a" keys together, and then enter the password defined in Preferences --> User Mode.

**Step 3.** Copy "CZ Popup.msi" to the workstation, double click "CZ Popup.msi" to install the popup. The add-on CZ Popup can also be installed silently and remotely using [Windows Group Policy](#).



**Step 4.** Click Start -> All Programs -> CZ Solution -> CZ Popup to run the popup. Enter the computer name or the IP Address of the computer that has Master Print Release Station - installed.




**Note:**

1. CZ Popup will be started automatically when user login next time.
2. Modify CZ Popup.msi package to include the name or IP address of the computer where you installed Master Print Release Station, so you don't have to enter it manually when you run CZ Print Job Agent the first time on each workstation. Visit [Step 1 of Windows Group Policy](#) how to use **Orca** to modify **CZ Popup.msi** .

**Scenario**

1. A user sends a print job from a workstation.
2. A popup window appears on the workstation (Windows, Mac OSX / Classic, or Linux client computer) showing the document name, printer name, total number of pages, and cost.




If the popup doesn't appear, see [FAQ 3](#).

**Note:** The users are allowed to

- (i) Change their print job names for the privacy, and (or)
- (ii) Create a password that they can use to release their print jobs on the print release station, and (or)
- (iii) Create a user id for their print jobs that they can use to show only their print jobs on the print release station (for some environments that users are allowed to use their own laptops to print or environments that user id is not unique).


The options "Require user to change the document name", "Require user to set password for the print job" and "Require user to set user id" can be selected in Preferences --> User Mode.





### 3.6 CZ Print Release Station User-Mode with Secure Card Reader Authenticator


**Step 1.** In Preferences --> User Mode, select “Use card containing xxxxx to release the print job”.



**Step 2.** In Menu Print Jobs, click "Switch to User Mode". You can switch back to Staff Mode by pressing "Alt" and "a" keys together, and then enter the password defined in Preferences --> User Mode.

#### Scenario

1. A user sends a print job from a workstation.
2. CZ Print Release Station holds the print job with detail print job information.
3. The user clicks the Print button.
4. A popup "Please swipe / insert your card" appears.



5. The user swipes or inserts the card to release the print job.


### 3.7 CZ Print Release Station User-Mode with Windows Active Directory Authentication

**Step 1.** In Preferences --> User Mode, select T “Use Windows Active Directory User Name and Password to release the print job”.

**Step 2.** In Menu Print Jobs, click "Switch to User Mode". You can switch back to Staff Mode by pressing "Alt" and "a" keys together, and then enter the password defined in Preferences --> User Mode.

#### Scenario

1. A user sends a print job from a workstation.
2. CZ Print Release Station holds the print job with detail print job information, but the job is not showed on the screen.



3. The user goes to the Print Release Station and enter the Windows Active Directory user name and password to show and release only his / her print job.

#### **4. Use Windows Group Policy to remotely install CZ Popup**

<http://www.czsolution.com/print-management/popupsilentinstall.htm>

#### **5. Frequently Asked Questions**

[http://www.czsolution.com/print-management/prs\\_faq.htm](http://www.czsolution.com/print-management/prs_faq.htm)